

insserv

Autorise un script init installé en lisant l'en-tête et calcule les dépendances.

Exemple

```
### BEGIN INIT INFO
# Provides : boot_facility_1 [ boot_facility_2 ...]
# Required-Start : boot_facility_1 [ boot_facility_2 ...]
# Required-Stop : boot_facility_1 [ boot_facility_2 ...]
# Should-Start : boot_facility_1 [ boot_facility_2 ...]
# Should-Stop : boot_facility_1 [ boot_facility_2 ...]
# X-Start-Before : boot_facility_1 [ boot_facility_2 ...]
# X-Stop-After : boot_facility_1 [ boot_facility_2 ...]
# Default-Start : run_level_1 [ run_level_2 ...]
# Default-Stop : run_level_1 [ run_level_2 ...]
# X-Interactive : true
# Short-Description : single_line_description
# Description : multiline_description
### END INIT INFO
```

insserv scanne /etc/insserv.conf et le contenu de /etc/insserv.conf.d/. exemple :

```
# All local filesystems are mounted
# (done during boot phase)
$local_fs boot

# Low level networking
$network network route

# Named is operational
$named named

# All remote filesystems are mounted
# (in some cases /usr may be remote).
$remote_fs $local_fs nfs

# System logger is operational
$syslog syslog

# All network daemons are running
$netdaemons portmap inetd

# Services which need to be interactive
<interactive> boot.crypto
```

OPTIONS

-v, --verbose mode verbeux
-c <config>, --config <config> Spécifier le chemin vers insserv.conf et insserv.conf.d
-o <path>, --override <path> l'en-tête trouvé dans ce chemin va remplacer l'en-tête existant dans les scripts.
-p <path>, --path <path> spécifier le dossier init.d
-n, --dryrun ne pas mettre à jour les liens
-r, --remove supprime les scripts listés de tous les runlevels
-d, --default utilise les runlevels par défaut dans les scripts.
-f, --force ignore si un service requis est manquant
[[/]path/to/init.d/] chemin relatif ou absolu vers le dossier des scripts. Défaut : /etc/init.d
[[/]path/to/init.d/] script ... Liste des scripts qui doivent être ajoutés aux runlevels
[[/]path/to/init.d/] script [,start=<lvl1,lvl2,...>] Liste des scripts qui doivent être ajoutés aux runlevels spécifiés
-r [[/]path/to/init.d/] script ... Liste de scripts qui devraient être supprimés des runlevels

Fichiers

/etc/insserv.conf Fichier de configuration
/etc/insserv.conf.d/ dossier contenant les fichiers de configurations
/etc/insserv/overrides/ Chemin pour remplacer les en-têtes des scripts
/etc/init.d/ le dossier contenant les scripts init
/etc/init.d/.depend.boot
/etc/init.d/.depend.start
/etc/init.d/.depend.stop Les fichiers de dépendances produits par insserv avec l'aide de startpar